



PL/PDF
User's Guide
v2.0.4



Contents

Introduction.....	5
Installation.....	5
Using PL/PDF.....	5
Documentation.....	5
Code Examples.....	5
Contact.....	5
Certification.....	6
GetCertKey.....	6
Administrative Commands.....	7
AddCJKFont.....	7
AddTTF.....	7
Init.....	7
Init1.....	8
GetVersion.....	8
nopAlias.....	8
SendDoc.....	8
SetAllMargin.....	9
SetAutoNewPage.....	9
SetCompress.....	9
SetDocAuthor.....	10
SetDocCreator.....	10
SetDocDisplayMode.....	10
SetDocKeywords.....	11
SetDocSubject.....	11
SetDocTitle.....	11
SetEncoding.....	11
SetFooterProcName.....	12
SetHeaderProcName.....	12
SetLeftMargin.....	12
SetNOLastpageProcName.....	13
SetPageNoEnd.....	13
SetPageNoStart.....	13
SetProtection.....	13
SetRightMargin.....	13
SetTopMargin.....	14
Navigation and Formatting Commands.....	15
CheckPageBreak.....	15
CurrentPageNumber.....	15
GetCurrentX.....	15
GetCurrentY.....	15
GetPageAvailableHeight.....	15
GetPageAvailableWidth.....	16
GetPageHeight.....	16
GetPageRightSpace.....	16
GetPageWidth.....	16
GetPrintFontName.....	16
GetPrintFontStyle.....	17
GetPrintFontSize.....	17
GetScaleFactor.....	17
GetTextWidth.....	17
LineBreak.....	17
NewPage.....	18
SetCurrentX.....	18



SetCurrentXY	18
SetCurrentY	18
Content Related Commands	19
AddLine2Pattern	19
AddRect2Pattern	19
AddEllipse2Pattern	19
AddCircle2Pattern	20
AddPolygon2Pattern	20
AddFileAnnot	20
AddHighLightAnnot	21
AddTextAnnot	21
AddStrikeOutAnnot	22
AddUnderlineAnnot	23
AttachFile	23
CrBookmark	23
CrInternalLink	24
CrTillingPattern	24
DrawCircle	24
DrawEllipse	25
DrawLine	25
DrawPolygon	25
DrawRect	25
DrawSector	26
EndClipping	26
GetImageProps	26
GetCellMargin	27
SetColor4Drawing	27
SetColor4Filling	27
GetLineWidth	27
GetRowHeight	27
GetTillingPatternColor	28
GetTillingPatternName	28
PrintCell	28
PrintFlowingText	29
PrintFlowingTextLimit	29
PrintImageCell	30
PutLink	30
PrintMultiLineCell	30
PrintText	31
PutImage	32
Row_Print	32
Row_Print2	33
Row_Print3	33
Row_Print4	34
SetCellMargin	34
SetColor4Drawing	34
SetColor4Drawing	35
SetColor4Filling	35
SetColor4Filling	35
SetColor4Text	35
SetColor4Text	36
SetDashPattern	36
SetJS	36
SetLineWidth	36
SetLinkDest	36
SetPrintFont	37



SetPrintFontSize.....	37
SetRotate.....	37
SetTillingPattern.....	38
StartClipping.....	38
Table Of Contents Commands.....	39
AddTOCItem.....	39
AddTOC.....	39
InTOC.....	39
GetTOCPageNum.....	40
PrintTOCItem.....	40
PrintTOCItem1.....	40
TOCInsertGap.....	40
TOCInsertGap1.....	41
PrintTOCTitle.....	41
PrintTOCTitle1.....	41
GetTOCItems.....	41
InsMoveTOC.....	41
InsMoveTOC1.....	42
Template related Commands.....	43
InsTemplate.....	43
UseTemplate.....	43
Acroform related Commands.....	44
AcroForm_AddTextField.....	44
AcroForm_AddChoiceField.....	45
AcroForm_AddPushbutton.....	45
AcroForm_AddRadiobuttonField.....	46
AcroForm_AddCheckBoxField.....	47
Version History.....	49
18-MAY-2005, v1.1.0.....	49
22-MAY-2005, v1.1.1.....	49
29-MAY-2005, v1.1.2.....	49
09-JUN-2005, v1.1.3.....	49
30-JUN-2005, v1.1.4.....	49
15-JUL-2005, v1.1.5.....	50
31-JUL-2005, v1.1.6.....	50
31-AUG-2005, v1.1.7.....	50
05-OCT-2005, v1.2.0.....	50
08-NOV-2005, v1.2.1.....	51
30-NOV-2005, v1.2.2.....	51
21-DEC-2005, v1.2.3.....	51
31-MAR-2006, v1.2.4.....	51
01-JUN-2006, v1.3.0.....	52
15-SEP-2006, v1.4.0.....	52
04-JAN-2007, v1.4.1.....	53
24-FEB-2007, v1.5.0.....	53
21-MAY-2007, v1.5.1.....	53
06-AUG-2007, v1.6.0.....	53
30-NOV-2007, v1.7.0.....	53
23-JUL-2008, v2.0.0.....	53



Introduction

PL/PDF is a PL/SQL based PDF document generator from Oracle databases. Use PL/PDF to quickly and easily develop applications with dynamic content but also quality presentation and printing capabilities.

Installation

Before using PL/PDF, make sure that the steps described in the Installation Guide were completed.

Using PL/PDF

Essentially, PL/PDF is a series of calls to PL/PDF procedures and functions from a PL/SQL script, package, procedure or function. If you are not familiar with the PL/SQL programming language, study the Oracle documentation.

Documentation

The PL/PDF documentation is available at: www.plpdf.com/23-927.html

Code Examples

PL/PDF code examples can be found at: <http://plpdf.com/23-4766.html>

Contact

Contact us at: info@plpdf.com



Certification

GetCertKey

Type: function

Description: Generates preliminary certification key. This function should be run once when the PL/PDF package is installed. The function generates a string that should be sent to info@plpdf.com. Our representatives will send a certificate key back that should be used as the return value in the `pl_pdf_cert.SetCertKey` function.

Parameters: -

Return: varchar2: Preliminary certificate key



Administrative Commands

AddCJKFont

Type: procedure

Description: Add CJK (Chinese/Japanese/Korean see <http://en.wikipedia.org/wiki/CJK>) font. The added font becomes available to the **SetPrintFont** procedure.

Parameters:

- p_name varchar2: name of font
 - o 'HeiseiKakuGo-W5': Japanese
 - o 'HYSMyeongJoStd-Medium-Acro': Korean
 - o 'MSungStd-Light-Acro': Chinese
 - o 'STSongStd-Light-Acro': Chinese

Return: -

AddTTF

Type: procedure

Description: Imports a TTF (True Type Font). The imported font becomes available to the **SetPrintFont** procedure. The font is stored as binary data in the PDF file.

Parameters:

- p_family varchar2: TTF name
- p_style varchar2 default null: Font style
 - o null: Regular
 - o B: Bold
 - o I: Italic
 - o BI or IB: Bold and Italic
- p_data t_addfont: Data structure necessary to insert the font. It contains the font definition binary file as well

Return: -

Init

Type: procedure

Description: Initializes generator program variables.

Parameters:

- p_orientation varchar2 default 'P': Orientation
 - o P: portrait
 - o L: landscape
- p_unit varchar2 default 'mm': Unit of measure. All the subsequent width or height parameters use this value as the unit of measure.
 - o pt: point (=1)
 - o mm: millimeter (=72/25.4)
 - o cm: centimeter (=72/2.54)
 - o in: inch (=72)
- p_format varchar2 default 'A4': Page format



- o a3: 841.89*1190.55
- o a4: 595.28*841.89
- o a5: 420.94*595.28
- o letter: 612*792
- o legal: 612*1008

Return: -

Init1

Type: procedure

Description: Initializes generator program variables.

Parameters:

- p_orientation varchar2 default 'P': Orientation
 - o P: portrait
 - o L: landscape
- p_unit varchar2 default 'mm': Unit of measure. All the subsequent width or height parameters use this value as the unit of measure.
 - o pt: point (=1)
 - o mm: millimeter (=72/25.4)
 - o cm: centimeter (=72/2.54)
 - o in: inch (=72)
- p_format plpdf_type.t_pageformat: see plpdf_const package for predefined pageformats

Return: -

GetVersion

Type: function

Description: Gets the version number of pl/pldf package

Parameters: -

Return: varchar2: number of current version

nopAlias

Type: procedure

Description: Defines the page number alias.

Parameters:

- p_alias varchar2 default '{nb}': Page number alias
- p_cp_alias varchar2 default '{cp}': Current page number alias
- p_format varchar2 default '{cp}/{nb}': Page numbering format

Return: -

SendDoc

Type: procedure



Description: Returns the generated PDF document. The document is closed and then returned in the OUT parameter.

Parameters:

- p_blob OUT NOCOPY BLOB: the generated document

Return: -

SetAllMargin

Type: procedure

Description: Sets the margin size.

Parameters:

- p_left number: Left margin size
- p_top number: Top margin size
- p_right number default -1: Right margin size. When it is set to -1 then the right margin will be the same as the left margin

Return: -

SetAutoNewPage

Type: procedure

Description: Enables or disables automatic page breaks. The p_margin parameter is only relevant when enabling automatic page breaks. It sets the bottom margin size under which an automatic page break is triggered.

Parameters:

- p_auto boolean: Automatic page break
 - o true: Enable
 - o false: Disable
- p_margin number default 0: Bottom margin size, if not set, then 1 cm

Return: -

SetCompress

Type: procedure

Description: Enables or disables the compression of PDF documents. By default compression is enabled.

Parameters:

- p_compress boolean: Compression
 - o True: Enable
 - o False: Disable
- p_method varchar2 default null: compress method
 - o plpdf_const.comp_FlateDecode: FlateDecode
 - o plpdf_const.comp_LZWDecode: LZWDecode

Return: -



SetDocAuthor

Type: procedure

Description: Sets the document author.

Parameters:

- p_author varchar2: Document author

Return: -

SetDocCreator

Type: procedure

Description: Sets the document creator.

Parameters:

- p_creator varchar2: Document creator

Return: -

SetDocDisplayMode

Type: procedure

Description: Sets how to display the document in a PDF viewer (e.g. Acrobat Reader).

Parameters:

- p_zoom varchar2: Layout view
 - o fullpage: fits as full page
 - o fullwidth: fits as full width
 - o real: fits in actual size
 - o default: displays according to the setting of the PDF viewer
- p_layout varchar2 default 'continuous': Page layout
 - o single: displays single pages
 - o continuous: displays pages continuously
 - o default: displays according to the setting of the PDF viewer
- p_hidemenubar boolean default false: A flag specifying whether to hide the viewer application's menu bar when the document is active.
- p_hidetoolbar boolean default false: A flag specifying whether to hide the viewer application's tool bars when the document is active.
- p_hidewindowui boolean default false: A flag specifying whether to hide user interface elements in the document's window (such as scroll bars and navigation controls), leaving only the document's contents displayed.
- p_displaydoctitle boolean default false: A flag specifying whether the window's title bar should display the document title taken from the Title entry of the document information dictionary.
- p_centerwindow boolean default false: A flag specifying whether to position the document's window in the center of the screen.
- p_fitwindow boolean default false: A flag specifying whether to resize the document's window to fit the size of the first displayed page.



Return: -

SetDocKeywords

Type: procedure

Description: Sets the document keywords.

Parameters:

- p_keywords varchar2: Keyword list

Return: -

SetDocSubject

Type: procedure

Description: Sets the document subject.

Parameters:

- p_subject varchar2: Document subject

Return: -

SetDocTitle

Type: procedure

Description: Sets the document title.

Parameters:

- p_title varchar2: Document title

Return:

SetEncoding

Type: procedure

Description: Sets Adobe Core character encoding (default code is cp1252) or Unicode TTF embending (AL32UTF8 database) with 'utf16'.

Parameters:

- p_enc varchar2: Character encoding code
 - o cp1250
 - o cp1251
 - o cp1252: this is the default, no need to set
 - o cp1253
 - o cp1254
 - o cp1255
 - o cp1256
 - o cp1257
 - o cp1258
 - o cp874



- o iso-8859-1
- o iso-8859-2
- o iso-8859-4
- o iso-8859-5
- o iso-8859-7
- o iso-8859-9
- o iso-8859-15
- o iso-8859-16
- o koi8_r
- o koi8_u
- o utf16: Unicode database (AL32UTF8) with Unicode TTF embending.

Return: -

SetFooterProcName

Type: procedure

Description: Sets the page footer procedure name. The program name passed as a parameter executes when the page footer is created. If **SetFooterProcName** is not executed before a page footer is created then the page footer will be empty.

Parameters:

- p_proc_name varchar2: Page footer procedure name
- p_height number: height of footer section

Return: -

SetHeaderProcName

Type: procedure

Description: Sets the page header procedure name. The program name passed as a parameter executes when the page header is created. If **SetHeaderProcName** is not executed before a page header is created then the page header will be empty.

Parameters:

- p_proc_name varchar2: Page header procedure name
- p_height number: height of header section

Return: -

SetLeftMargin

Type: procedure

Description: Sets the left margin size.

Parameters:

- p_margin number: Margin size

Return: -



SetNOLastpageProcName

Type: procedure

Description: Sets the procedure name that runs before a page is closed. The procedure does not run for the last page. The program name passed as a parameter must be a stand-alone procedure.

Parameters:

- p_proc_name varchar2: Procedure name

Return: -

SetPageNoEnd

Type: procedure

Description: Sets end of page numbering to the current page, see **SetPageNoStart**.

Parameters: -

Return: -

SetPageNoStart

Type: procedure

Description: Sets start of page numbering to the current page.

Parameters: -

Return: -

SetProtection

Type: procedure

Description: Allows to protect the PDF document.

Parameters:

- p_print_perm Boolean default false: print the PDF
- p_modify_perm Boolean default false: modify the PDF
- p_copy_perm boolean default false: copy content
- p_annot_forms_perm Boolean default false: add annotations and forms
- p_user_pass varchar2 default null: user password
- p_owner_pass varchar2 default null: owner password

Return: -

SetRightMargin

Type: procedure



Description: Sets the right margin size.

Parameters:

- p_margin number: Margin size

Return: -

SetTopMargin

Type: procedure

Description: Sets the top margin size.

Parameters:

- p_margin number: Margin size

Return: -



Navigation and Formatting Commands

CheckPageBreak

Type: function

Description: If the height would cause an overflow, add a new page immediately, and return true

Parameters:

- p_h number: height for check page overflow
- p_newpage boolean default true: do NewPage procedure

Return: boolean:

- true: overflow is reached
- false: don't reach overflow

CurrentPageNumber

Type: function

Description: Returns the page number of the current page.

Parameters:

Return: number: Page number of the current page

GetCurrentX

Type: function

Description: Gets the X coordinate of the cursor

Parameters: -

Return: number: X coordinate

GetCurrentY

Type: function

Description: Gets the Y coordinate of the cursor.

Parameters: -

Return: number: Y coordinate

GetPageAvailableHeight

Type: function

Description: Gets the available height (without margins) of actual page.



Parameters: -

Return: number

GetPageAvailableWidth

Type: function

Description: Gets the available width (without margins) of actual page.

Parameters: -

Return: number

GetPageHeight

Type: function

Description: Gets the height of actual page.

Parameters: -

Return: number

GetPageRightSpace

Type: function

Description: Gets the available width (without margins) of actual page from current position.

Parameters: -

Return: number

GetPageWidth

Type: function

Description: Gets the width of actual page.

Parameters: -

Return: number

GetPrintFontName

Type: function

Description: Get the current font type.

Parameters: -

Return: varchar2



GetPrintFontStyle

Type: function

Description: Get the current font style.

Parameters: -

Return: varchar2

GetPrintFontSize

Type: function

Description: Get the current font size.

Parameters: -

Return: varchar2

GetScaleFactor

Type: function

Description: Get the current scale factor.

Parameters: -

Return: number

GetTextWidth

Type: function

Description: Returns the width of the parameter text.

Parameters:

- p_s varchar2: Text

Return: number: The width of the text in the unit of measure specified in **Init**

LineBreak

Type: procedure

Description: Line break. Cursor is placed at the start of the next line.

Parameters:

- p_h number default NULL: Height of the line break. If not set, then the last printed cells height is the height by default

Return: -



NewPage

Type: procedure

Description: Creates a new page. If no orientation is given then the orientation specified in **Init** will be used. If a page was previously open, a page break is initiated and the cursor is placed at the top left corner of the new page.

Parameters:

- p_orientation varchar2 default NULL: Page orientation
 - o P: Portrait
 - o L: Landscape

Return: -

SetCurrentX

Type: procedure

Description: Places the cursor at the X coordinate

Parameters:

- p_x number default 0: X coordinate

Return: -

SetCurrentXY

Type: procedure

Description: Places the cursor at the X and Y coordinate

Parameters:

- p_x number: X coordinate
- p_y number: Y coordinate

Return: -

SetCurrentY

Type: procedure

Description: Places the cursor at the Y coordinate

Parameters:

- p_y number default 0: Y coordinate
- p_cr boolean default true: X position returns to beginning of line

Return: -



Content Related Commands

AddLine2Pattern

Type: procedure

Description: Add a line to the pattern (see CrTillingPattern).

Parameters:

- p_name varchar2: name of pattern
- p_x1 number: X coordinate for the start of the line
- p_y1 number: Y coordinate for the start of the line
- p_x2 number: X coordinate for the end of the line
- p_y2 number: Y coordinate for the end of the line

Return: -

AddRect2Pattern

Type: procedure

Description: Add a rectangle to the pattern (see CrTillingPattern).

Parameters:

- p_name varchar2: name of pattern
- p_x number: X coordinate for the top left corner of the rectangle
- p_y number: Y coordinate for the top left corner of the rectangle
- p_w number: The width of the rectangle
- p_h number: The height of the rectangle
- p_style varchar2 default NULL: Style
 - o D: No fill, border line
 - o F: Fill, no border line
 - o DF or FD: Fill and border line

Return: -

AddEllipse2Pattern

Type: procedure

Description: Add a ellipse to the pattern (see CrTillingPattern).

Parameters:

- p_name varchar2: name of pattern
- p_x number: X coordinate of the center of the ellipse
- p_y number: Y coordinate of the center of the ellipse
- p_rx number: horizontal radius of the ellipse
- p_ry number: vertical radius of the ellipse
- p_style varchar2 default 'D': Style
 - o D: No fill, border line
 - o F: Fill, no border line
 - o DF or FD: Fill and border line



Return: -

AddCircle2Pattern

Type: procedure

Description: Add a circle to the pattern (see CrTillingPattern).

Parameters:

- p_name varchar2: name of pattern
- p_x number: X coordinate of the center of the circle
- p_y number: Y coordinate of the center of the circle
- p_r number: the radius of the circle
- p_style varchar2 default 'D': Style
 - o D: No fill, border line
 - o F: Fill, no border line
 - o DF or FD: Fill and border line

Return: -

AddPolygon2Pattern

Type: procedure

Description: Add a polygon to the pattern (see CrTillingPattern).

Parameters:

- p_name varchar2: name of pattern
- p_points plpdf_type.t_points: set of ordered points
- p_style varchar2 default 'D': Style
 - o D: No fill, border line
 - o F: Fill, no border line
 - o DF or FD: Fill and border line

Return: -

AddFileAnnot

Type: procedure

Description: Add File annotation to the current page.

Parameters:

- p_name varchar2 default 'PushPin': The name of an icon to be used in displaying the annotation.
 - o PushPin
 - o Graph
 - o Paperclip
 - o Tag
- p_contents varchar2: The text to be displayed in the pop-up window when the annotation is opened.
- p_x number: X coordinate of the annotation
- p_y number: Y coordinate of the annotation



- p_filename varchar2: name of file
- p_fileblob blob: file
- p_label varchar2 default null: The text label to be displayed in the title bar of the annotation's pop-up window when open and active.
- p_color plpdf_type.t_color default null: This color will be used for the following purposes:
 - o The background of the annotation's icon when closed
 - o The title bar of the annotation's pop-up window
 - o The border of a link annotation

Return: -

AddHighLightAnnot

Type: procedure

Description: Add HighLight annotation to the current page.

Parameters:

- p_contents varchar2: The text to be displayed in the pop-up window when the annotation is opened.
- p_x number: X coordinate of the annotation
- p_y number: Y coordinate of the annotation
- p_w number: width of the annotation
- p_h number: height of the annotation
- p_label varchar2 default null: The text label to be displayed in the title bar of the annotation's pop-up window when open and active.
- p_color plpdf_type.t_color default null: This color will be used for the following purposes:
 - o The background of the annotation's icon when closed
 - o The title bar of the annotation's pop-up window
 - o The border of a link annotation
- p_popup_x number default null: X coordinate of the pop-up window
- p_popup_y number default null: Y coordinate of the pop-up window
- p_popup_w number default null: width of the pop-up window
- p_popup_h number default null: height of the pop-up window
- p_open boolean default false: A flag specifying whether the pop-up window should initially be displayed open.

Return: -

AddTextAnnot

Type: procedure

Description: Add Text annotation to the current page.

Parameters:

- p_name varchar2 default 'Note': The name of an icon to be used in displaying the annotation.
 - o Comment
 - o Key
 - o Note



- o Help
- o NewParagraph
- o Paragraph
- o Insert
- p_contents varchar2: The text to be displayed in the pop-up window when the annotation is opened.
- p_x number: X coordinate of the annotation
- p_y number: Y coordinate of the annotation
- p_label varchar2 default null: The text label to be displayed in the title bar of the annotation's pop-up window when open and active.
- p_color plpdf_type.t_color default null: This color will be used for the following purposes:
 - o The background of the annotation's icon when closed
 - o The title bar of the annotation's pop-up window
 - o The border of a link annotation
- p_popup_x number default null: X coordinate of the pop-up window
- p_popup_y number default null: Y coordinate of the pop-up window
- p_popup_w number default null: width of the pop-up window
- p_popup_h number default null: height of the pop-up window
- p_open boolean default false: A flag specifying whether the pop-up window should initially be displayed open.

Return: -

AddStrikeOutAnnot

Type: procedure

Description: Add StrikeOut annotation to the current page.

Parameters:

- p_contents varchar2: The text to be displayed in the pop-up window when the annotation is opened.
- p_x number: X coordinate of the annotation
- p_y number: Y coordinate of the annotation
- p_w number: width of the annotation
- p_h number: height of the annotation
- p_label varchar2 default null: The text label to be displayed in the title bar of the annotation's pop-up window when open and active.
- p_color plpdf_type.t_color default null: This color will be used for the following purposes:
 - o The background of the annotation's icon when closed
 - o The title bar of the annotation's pop-up window
 - o The border of a link annotation
- p_popup_x number default null: X coordinate of the pop-up window
- p_popup_y number default null: Y coordinate of the pop-up window
- p_popup_w number default null: width of the pop-up window
- p_popup_h number default null: height of the pop-up window
- p_open boolean default false: A flag specifying whether the pop-up window should initially be displayed open.

Return: -



AddUnderlineAnnot

Type: procedure

Description: Add Underline annotation to the current page.

Parameters:

- p_contents varchar2: The text to be displayed in the pop-up window when the annotation is opened.
- p_x number: X coordinate of the annotation
- p_y number: Y coordinate of the annotation
- p_w number: width of the annotation
- p_h number: height of the annotation
- p_label varchar2 default null: The text label to be displayed in the title bar of the annotation's pop-up window when open and active.
- p_color plpdf_type.t_color default null: This color will be used for the following purposes:
 - o The background of the annotation's icon when closed
 - o The title bar of the annotation's pop-up window
 - o The border of a link annotation
- p_popup_x number default null: X coordinate of the pop-up window
- p_popup_y number default null: Y coordinate of the pop-up window
- p_popup_w number default null: width of the pop-up window
- p_popup_h number default null: height of the pop-up window
- p_open boolean default false: A flag specifying whether the pop-up window should initially be displayed open.

Return: -

AttachFile

Type: procedure

Description: Attachs a file to the PDF document.

Parameters:

- p_filename varchar2: name of file
- p_fileblob blob: file
- p_desc varchar2 default null: description of file

Return: -

CrBookmark

Type: procedure

Description: Create a bookmark in the PDF document. Bookmarks are displayed in the PDF viewer program (e.g. Acrobat Reader).

Parameters:

- p_txt varchar2: Text of the bookmark
- p_level number default 0: Bookmark level, 0 is the highest level
- p_y number default 0: Y coordinate of the bookmark within the current page. -1 denotes the cursor position.

Return: -

CrInternalLink

Type: function

Description: Creates an internal link, and returns its ID. An internal link can be used to take the cursor to another place within the document by clicking over it.

Parameters:

Return: number: The ID of the internal link

CrTilingPattern

Type: procedure

Description: Starts of define a "Tiling Pattern". Tiling patterns consist of a small graphical figure (called a pattern cell) that is replicated at fixed horizontal and vertical intervals to fill the area to be painted.

Add "graphical figure" to pattern:

- AddLine2Pattern: add a line to pattern
- AddRect2Pattern: add a rectangle to pattern
- AddEllipse2Pattern: add a ellipse to pattern
- AddCircle2Pattern: add a circle to pattern
- AddPolygon2Pattern: add a polygon to pattern

Parameters:

- p_name varchar2: name of pattern
- p_width number: width of pattern cell
- p_height number: height of pattern cell

Return: -

DrawCircle

Type: procedure

Description: Draws a circle on the current page

Parameters:

- p_x number: X coordinate of the center of the circle
- p_y number: Y coordinate of the center of the circle
- p_r number: the radius of the circle
- p_style varchar2 default NULL: Style
 - o D: No fill, border line
 - o F: Fill, no border line
 - o DF or FD: Fill and border line

Return: -



DrawEllipse

Type: procedure

Description: Draws an ellipse on the current page.

Parameters:

- p_x number: X coordinate of the center of the ellipse
- p_y number: Y coordinate of the center of the ellipse
- p_rx number: horizontal radius of the ellipse
- p_ry number: vertical radius of the ellipse
- p_style varchar2 default 'D': Style
 - o D: No fill, border line
 - o F: Fill, no border line
 - o DF or FD: Fill and border line

Return: -

DrawLine

Type: procedure

Description: Draws a line between the two positions on the page.

Parameters:

- p_x1 number: X coordinate for the start of the line
- p_y1 number: Y coordinate for the start of the line
- p_x2 number: X coordinate for the end of the line
- p_y2 number: Y coordinate for the end of the line

Return: -

DrawPolygon

Type: procedure

Description: Draws a lines (polygon) between the points on the page.

Parameters:

- p_points plpdf_type.t_points: set of ordered points
- p_style varchar2 default 'D': Style
 - o D: No fill, border line
 - o F: Fill, no border line
 - o DF or FD: Fill and border line

Return: -

DrawRect

Type: procedure

Description: Draws a rectangle on the page.

Parameters:



- p_x number: X coordinate for the top left corner of the rectangle
- p_y number: Y coordinate for the top left corner of the rectangle
- p_w number: The width of the rectangle
- p_h number: The height of the rectangle
- p_style varchar2 default NULL: Style
 - o D: No fill, border line
 - o F: Fill, no border line
 - o DF or FD: Fill and border line

Return: -

DrawSector

Type: procedure

Description: Draws a sector on the current page.

Parameters:

- p_xc number: X coordinate of the center of the sector
- p_yc number: Y coordinate of the center of the sector
- p_r number: Radius of the sector
- p_a number: Starting point of the sector
- p_b number: End point of the sector
- p_style varchar2 default 'FD': Style
 - o D: No fill, border line
 - o F: Fill, no border line
 - o DF vagy FD: Fill and border line
- p_cw boolean default true: Draw direction
 - o true: Clockwise
 - o false: Anti-clockwise
- p_o number default 90

Return: -

EndClipping

Type: procedure

Description: see StartClipping.

Parameters: -

Return: -

GetImageProps

Type: function

Description: Returns with image properties.

Parameters: p_data blob: image

Return: plpdf_type.t_imageprops



GetCellMargin

Type: function

Description: Gets the cell margin size.

Parameters: -

Return: number

GetColor4Drawing

Type: function

Description: Gets the line color for objects.

Parameters: -

Return: plpdf_type.t_color

GetColor4Filling

Type: function

Description: Gets the filling color for objects.

Parameters: -

Return: plpdf_type.t_color

GetColor4Text

Type: function

Description: Gets the color for texts.

Parameters: -

Return: plpdf_type.t_color

GetLineWidth

Type: function

Description: Gets the current line size.

Parameters: -

Return: number

GetRowHeight

Type: function

Description: Returns with height of row (see: Row_Print2).



Parameters:

- p_data plpdf_type.t_row_datas: Data shown in the cells
- p_width plpdf_type.t_row_widths: Width of the cells
- p_maxline plpdf_type.t_row_maxlines: Maximum number of lines in a multi-line cell
- p_h number default 5: Height of the cells

Return: number

GetTillingPatternColor

Type: function

Description: Gets the color of filling pattern for objects.

Parameters: -

Return: plpdf_type.t_color

GetTillingPatternName

Type: function

Description: Gets the name of filling pattern for objects.

Parameters: -

Return: varchar2

PrintCell

Type: procedure

Description: Draws a rectangle cell with text inside. The rectangle may have a border and fill color specified.

Parameters:

- p_w number default 0: Rectangle width, if 0 then the rectangle will extend till the right margin
- p_h number default 0: Rectangle height
- p_txt varchar2 default NULL: Text
- p_border varchar2 default '0': Rectangle border
 - o 0: no border
 - o 1: outline border
 - o L: left side border
 - o T: top side border
 - o R: right side border
 - o B: bottom side borderOr a combination of L, T, R and B
- p_ln number default 0: Cursor position after the cell is printed
 - o 0: Beside the cell
 - o 1: New line



- o 2: Under the cell
- p_align varchar2 default NULL: Text alignment
 - o L: left
 - o R: right
 - o C: center
 - o J: Force Justification
- p_fill number default 0: Fill
 - o 0: no fill
 - o 1: fill with current fill color
- p_link varchar2 default NULL: Link related to the text, can be a URL or an internal link ID
- p_clipping number default 1: Clipping text
 - o 0: no clipping
 - o 1: clipping

Return: -

PrintFlowingText

Type: procedure

Description: Prints text continuously. Text is wrapped according to the p_min_x and p_max_x.

Parameters:

- p_h number: Height
- p_txt varchar2: Text
- p_link varchar2 default NULL: URL or internal link ID
- p_align varchar2 default NULL: Text alignment
- p_clipping number default 1: Clipping text
 - o 0: no clipping
 - o 1: clipping

Return: -

PrintFlowingTextLimit

Type: procedure

Description: Prints text continuously. Text is wrapped according to the right margin.

Parameters:

- p_h number: Height
- p_txt varchar2: Text
- p_min_x number default 0: min X position, 0 means the limit is the left margin
- p_max_x number default 0: max X position, 0 means the limit is the right margin
- p_link varchar2 default NULL: URL or internal link ID
- p_clipping number default 1: Clipping text
 - o 0: no clipping
 - o 1: clipping



Return: -

PrintImageCell

Type: procedure

Description: Print an image with frame.

Parameters:

- p_w number: Width of frame
- p_h number: Height of frame
- p_name varchar2: name of image
- p_data blob: image
- p_margin number default 0: margin size of frame
- p_border varchar2 default '0': Rectangle border
 - o 0: no border
 - o 1: outline border
 - o L: left side border
 - o T: top side border
 - o R: right side border
 - o B: bottom side border

Or a combination of L, T, R and B

- p_ln number default 0: Cursor position after the cell is printed
 - o 0: Beside the cell
 - o 1: New line
 - o 2: Under the cell
- p_fill number default 0: Fill
 - o 0: no fill
 - o 1: fill with current fill color
- p_link varchar2 default NULL: URL or internal link ID
- p_type varchar2 default null: when use Oracle InterMedia then ignore this param, when does not use Oracle InterMedia then JPG or PNG, null means JPG

Return: -

PutLink

Type: procedure

Description: Puts a link area on the page that point to an internal link.

Parameters:

- p_x number: X coordinate of the top left corner of the area
- p_y number: Y coordinate of the top left corner of the area
- p_w number: Link area width
- p_h number: Link area height
- p_link varchar2: Internal link ID returned by **CrInternalLink**

Return: -

PrintMultiLineCell

Type: procedure



Description: Draws a multi line cell.

Note: When using Oracle without Java (for example Oracle XE), only the use of standard JPG images is supported. PL/PDF uses Oracle InterMedia to convert images. Oracle InterMedia requires Java.

Parameters:

- p_w number default 0: Rectangle width, if 0 then the rectangle will extend till the right margin
- p_h number default 0: Rectangle height
- p_txt varchar2: Text
- p_border varchar2 default '0': Rectangle border
 - o 0: no border
 - o 1: outline border
 - o L: left side border
 - o T: top side border
 - o R: right side border
 - o B: bottom side borderOr a combination of L, T, R and B
- p_align varchar2 default 'J': Text alignment
 - o L: left
 - o R: right
 - o C: center
 - o J: Force Justification
- p_fill number default 0: Fill
 - o 0: no fill
 - o 1: fill with current fill color
- p_maxline number default 0: Maximum number of lines displayed. If 0 then all lines will be displayed.
- p_link varchar2 default NULL: Link related to the text, can be a URL or an internal link ID
- p_clipping number default 1: Clipping text
 - o 0: no clipping
 - o 1: clipping
- p_indent number default 0: Indent
- p_ln number default 1: Cursor position after the cell is printed
 - o 0: Beside the cell
 - o 1: New line
 - o 2: Under the cell

Return: -

PrintText

Type: procedure

Description:

Parameters: Prints a text starting from the specified position.

- p_x number: X coordinate for the start of the text
- p_y number: Y coordinate for the start of the text
- p_txt varchar2: Text



Return: -

PutImage

Type: procedure

Description: Inserts an image (JPG, BMP, PNG, etc.) from a BLOB variable into the current page.

Note: When the source of image is a query, then the "FOR UPDATE" clause must be used.

Also, when using Oracle without Java (for example Oracle XE), only the use of standard JPG images is supported. PL/PDF uses Oracle InterMedia to convert images. Oracle InterMedia requires Java.

Parameters:

- p_name varchar2: Image name or ID
- p_data blob: Variable containing the image as binary data
- p_x number: X coordinate of the image
- p_y number: Y coordinate of the image
- p_w number default 0: Image width, if 0 then the image is displayed in its actual width
- p_h number default 0: Image height, if 0 then the image is displayed in its actual height
- p_link varchar2 default NULL: URL or internal link ID
- p_type varchar2 default null: when use Oracle InterMedia then ignore this param, when does not use Oracle InterMedia then JPG or PNG, null means JPG

Return: -

Row_Print

Type: procedure

Description: Prints a full row in the PDF document. The rows consist of multi-line cells. The row's height is set according to the largest cell.

Parameters:

- p_data plpdf_type.t_row_datas: Data shown in the cells
- p_width plpdf_type.t_row_widths: Width of the cells
- p_align plpdf_type.t_row_aligns: Alignment of the cells
- p_h number default 5: Height of the cells
- p_fill number default 0: Fill
 - o 0: no fill
 - o 1: fill with current fill color
- p_min_height number default 0: Minimal height of row, 0 means not use this parameter
- p_clipping number default 1: Clipping text
 - o 0: no clipping
 - o 1: clipping

Return: -



Row_Print2

Type: procedure

Description: Prints a full row in the PDF document. The rows consist of multi-line cells. The row's height is set according to the largest cell.

Parameters:

- p_data plpdf_type.t_row_datas: Data shown in the cells
- p_border plpdf_type.t_row_borders: Border array of the cells
- p_width plpdf_type.t_row_widths: Width of the cells
- p_align plpdf_type.t_row_aligns: Alignment of the cells
- p_style plpdf_type.t_row_styles: Style of the cells
- p_maxline plpdf_type.t_row_maxlines: Maximum number of lines in a multi-line cell
- p_h number default 5: Height of the cells
- p_fill number default 0: Fill
 - o 0: no fill
 - o 1: fill with current fill color
- p_min_height number default 0: Minimal height of row, 0 means not use this parameter
- p_clipping number default 1: Clipping text
 - o 0: no clipping
 - o 1: clipping

Return: -

Row_Print3

Type: procedure

Description: Prints a full row in the PDF document. The rows consist of multi-line cells. The row's height is set according to the largest cell.

Parameters:

- p_data plpdf_type.t_row_datas: Data shown in the cells
- p_border plpdf_type.t_row_borders: Border array of the cells
- p_width plpdf_type.t_row_widths: Width of the cells
- p_align plpdf_type.t_row_aligns: Alignment of the cells
- p_style plpdf_type.t_row_styles: Style of the cells
- p_maxline plpdf_type.t_row_maxlines: Maximum number of lines in a multi-line cell
- p_links plpdf_type.t_row_links: Links of the cells
- p_h number default 5: Height of the cells
- p_fill number default 0: Fill
 - o 0: no fill
 - o 1: fill with current fill color
- p_min_height number default 0: Minimal height of row, 0 means not use this parameter
- p_clipping number default 1: Clipping text
 - o 0: no clipping
 - o 1: clipping

Return: -



Row_Print4

Type: procedure

Description: Prints a full row in the PDF document. The rows consist of multi-line cells. The row's height is set according to the largest cell.

Parameters:

- p_data plpdf_type.t_row_datas: Data shown in the cells
- p_border plpdf_type.t_row_borders: Border array of the cells
- p_width plpdf_type.t_row_widths: Width of the cells
- p_align plpdf_type.t_row_aligns: Alignment of the cells
- p_font plpdf_type.t_row_fonts: Font of the cells (Family is required)
- p_maxline plpdf_type.t_row_maxlines: Maximum number of lines in a multi-line cell
- p_links plpdf_type.t_row_links: Links of the cells
- p_h number default 5: Height of the cells
- p_fill Plpdf_Type.t_row_filles: Fill colors
- p_min_height number default 0: Minimal height of row, 0 means that this parameter is not used
- p_clipping number default 1: Clipping text
 - o 0: no clipping
 - o 1: clipping

Return: -

SetCellMargin

Type: procedure

Description: Sets the cell margin size.

Parameters:

- p_margin number: Margin size

Return: -

SetColor4Drawing

Type: procedure

Description: Sets the line color for objects (line, rectangle, circle etc.) inserted after this statement. Colors must be specified according to the RGB pallet.

Parameters:

- p_r number: Red component code, can be between 0 and 255
- p_g number default -1: Green component code, can be between 0 and 255
- p_b number default -1: Blue component code, can be between 0 and 255

Return: -



SetColor4Drawing

Type: procedure

Description: Sets the line color for objects (line, rectangle, circle etc.) inserted after this statement. Colors must be specified according to the RGB pallet.

Parameters:

- p_color plpdf_type.t_color: color

Return: -

SetColor4Filling

Type: procedure

Description: Sets the fill color for objects inserted after this statement. Colors must be specified according to the RGB pallet.

Parameters:

- p_r number: Red component code, can be between 0 and 255
- p_g number default -1: Green component code, can be between 0 and 255
- p_b number default -1: Blue component code, can be between 0 and 255

Return: -

SetColor4Filling

Type: procedure

Description: Sets the fill color for objects inserted after this statement. Colors must be specified according to the RGB pallet.

Parameters:

- p_color plpdf_type.t_color: color

Return: -

SetColor4Text

Type: procedure

Description: Sets the text color for objects inserted after this statement. Colors must be specified according to the RGB pallet.

Parameters:

- p_r number: Red component code, can be between 0 and 255
- p_g number default -1: Green component code, can be between 0 and 255
- p_b number default -1: Blue component code, can be between 0 and 255

Return: -



SetColor4Text

Type: procedure

Description: Sets the text color for objects inserted after this statement. Colors must be specified according to the RGB pallet.

Parameters:

- p_color plpdf_type.t_color: color

Return: -

SetDashPattern

Type: procedure

Description: Sets the dash pattern for lines inserted after this statement. Call the procedure without parameter to restore normal drawing.

Parameters:

- p_line number default null: length of dashes
- p_noline number default null: length of gaps

Return: -

SetJS

Type: procedure

Description: add JavaScript inside the PDF. See Acrobat JavaScript Reference

Parameters:

- p_text varchar2: JavaScript source code.

Return: -

SetLineWidth

Type: procedure

Description: Sets the thickness of lines drawn after this statement. If no thickness is set then it is 0.2 mm by default.

Parameters:

- p_width number: Line thickness

Return: -

SetLinkDest

Type: procedure



Description: Sets the destination page and position for the internal link.

Parameters:

- p_link number: Internal link ID returned by **CrInternalLink**
- p_y number default 0: Y position on the page, if -1 then the current Y coordinate, if 0 then the top of the page
- p_page number default -1: Page number, if -1 then the current page

Return: -

SetPrintFont

Type: procedure

Description: Sets the font and its properties.

Parameters:

- p_family varchar2 default NULL: Font type
 - o Helvetica (Arial, Sans Serif)
 - o Courier
 - o Times (Serif)
 - o Symbol
 - o ZapfDingBats

If TTF fonts were added using the **AddTTF** procedure then they may be used here as well.

- p_style varchar2 default NULL: Font style
 - o null: Regular
 - o B: Bold
 - o I: Italic
 - o U: Underline

The styles may be combined (i.e. BI will be Bold and Italic)

- p_size number default 0: Font size, by default it is 12

Return: -

SetPrintFontSize

Type: procedure

Description: Sets the font size. All other font properties remain unchanged.

Parameters:

- p_size number: Font size

Return: -

SetRotate

Type: procedure

Description: Sets the degree of rotation. Text and images can both be rotated.



Parameters:

- p_angle number: Angle/degree of rotation
- p_x number default -1: X coordinate of the rotation point, if -1 then the X coordinate of the cursor
- p_y number default -1: Y coordinate of the rotation point, if -1 then the Y coordinate of the cursor

Return: -

SetTillingPattern

Type: procedure

Description: Sets the fill pattern for objects inserted after this statement.

Parameters:

- p_name varchar2: name of pattern (see CrTillingPattern)
- p_color plpdf_type.t_color: color of "graphical figures"

Return: -

StartClipping

Type: procedure

Description: Starts a clipping frame. The clipping limits the region that can be paint. The clipping affects for objects wich located between StartClipping and EndClipping.

Parameters:

- p_x number: X coordinate for the start of the clipping frame
- p_y number: Y coordinate for the start of the clipping frame
- p_w number: height of clipping frame
- p_h number: width of clipping frame

Return: -



Table Of Contents Commands

AddTOCItem

Type: procedure

Description: Add Table of Contents item.

Parameters:

- p_txt varchar2: label of TOC item
- p_level number default 0: level, 0 is the highest level
- p_y number default -1: Y position on the page, if -1 then the current Y coordinate, if 0 then the top of the page
- p_page number default -1: Page number, if -1 then the current page
- p_add_link boolean default true: create link from TOC item to page
- p_add_bookmark boolean default false: create bookmark for TOC item

Return: -

AddTOC

Type: procedure

Description: Construct Table of Contents.

Parameters:

- p_item_height number default null: height of TOC item cell
- p_stop_footer boolean default true: do not print footer (by executing the footer procedure) in TOC
- p_title_font_family varchar2 default null: font family of title text
- p_title_font_style varchar2 default null: font style (bold, italic, etc.) of title text
- p_title_font_size number default 0: font size of title text
- p_title_height number default null: height of title's cell
- p_title_text varchar2 default null: title of TOC if title is null then no title will be printed
- p_title_body_gap number default 0: gap between title and TOC items
- p_item_font_family varchar2 default null: font family of TOC items
- p_item_font_style varchar2 default null: font style of TOC items
- p_item_font_size number default 0: font size of TOC items
- p_level_indent number default 0: indent size for levels
- p_separator varchar2 default ' ': filler between TOC item and page number
- p_move_to number default 0: move TOC pages to a new page number in PDF
- p_custom_proc varchar2 default null: if a custom procedure is used for creating TOC then it is the name of procedure

Return: -

InTOC

Type: function



Description: Is current position inside TOC.

Parameters: -

Return: boolean

GetTOCPageNum

Type: function

Description: If actual position is inside TOC then returns page number (first page of TOC returns 1).

Parameters: -

Return: number

PrintTOCItem

Type: procedure

Description: Print a TOC Item into the PDF (for creating custom TOC).

Parameters:

- p_item plpdf_type.tr_toc: TOC Item
- p_toc_level_indent number default 0: indent size for levels
- p_toc_item_height number: height of TOC item cell
- p_toc_separator varchar2 default ' ': filler between TOC item and page number

Return: -

PrintTOCItem1

Type: procedure

Description: Print a TOC Item into the PDF with settings specified in **AddTOC** (for creating custom TOC)

Parameters:

- p_item plpdf_type.tr_toc: TOC Item

Return: -

TOCInsertGap

Type: procedure

Description: Insert gap between title and items (for creating custom TOC).

Parameters:

- p_toc_title_body_gap number: size of gap



Return: -

TOCInsertGap1

Type: procedure

Description: Insert gap between title and items with settings specified in **AddTOC** (for creating custom TOC).

Parameters: -

Return: -

PrintTOCTitle

Type: procedure

Description: Insert title section in TOC (for creating custom TOC).

Parameters:

- p_toc_title_text varchar2 default null: text of title
- p_toc_title_height number default null: height of title's cell
- p_level number default 0: level, 0 is the highest level

Return: -

PrintTOCTitle1

Type: procedure

Description: Insert title section in TOC with settings specified in **AddTOC** (for creating custom TOC).

Parameters: -

Return: -

GetTOCItems

Type: function

Description: Returns array of TOC items (for creating custom TOC).

Parameters: -

Return: plpdf_type.t_toc

InsMoveTOC

Type: procedure

Description: Move TOC to specified page number.

Parameters:

- p_move_to number: page number



Return: -

InsMoveTOC1

Type: procedure

Description: Move TOC to specified page number using p_move_to parameter in **AddTOC**.

Parameters: -

Return: -



Template related Commands

InstTemplate

Type: function

Description: Insert a template into the pdf.

Parameters:

- p_tpl plpdf_type.tr_tpl_data: template data

Return: number (Template ID)

UseTemplate

Type: procedure

Description: Use a template.

Parameters:

- p_tplidx number: template ID
- p_fittopage boolean default true: fit template to page size

Return: -



Acroform related Commands

An interactive form (sometimes referred to as an AcroForm) is a collection of fields for gathering information interactively from the user. A PDF document may contain any number of fields appearing on any combination of pages, all of which make up a single, global interactive form spanning the entire document.

AcroForm_AddTextField

Type: procedure

Description: Add TextField.

Parameters:

- p_name varchar2: identifier of object
- p_value varchar2 default null: value of field
- p_default_value varchar2 default null: The default value to which the field reverts when a reset-form action is executed
- p_maxlength number default 0: The maximum length of the field's text, in characters
- p_multiline boolean default false: If set, the field may contain multiple lines of text
- p_password boolean default false: If set, the field is intended for entering a secure password that should not be echoed visibly to the screen
- p_read_only boolean default false: If set, the user may not change the value of the field
- p_required boolean default false: If set, the field must have a value at the time it is exported by a submit-form action
- p_noexport boolean default false: If set, the field must not be exported by a submitform action
- p_print boolean default false: If set, print the field when the page is printed
- p_x number: X coordinate for the field
- p_y number: Y coordinate for the field
- p_width number: The width of the field
- p_height number: The height of the field
- p_align varchar2 default null: Text alignment
 - o L: left (default)
 - o R: right
 - o C: center
- p_border_width number default 0: width of border of the field
- p_border_color plpdf_type.t_color default plpdf_const.Black: color of border
- p_font_size_auto boolean default false: If set, the text's size is automatic else use size of current font.
- p_hint varchar2 default null: The user name to be used when generating error or status messages for the field

Return: -



AcroForm_AddChoiceField

Type: procedure

Description: Add ChoiceField.

Parameters:

- p_name varchar2: identifier of object
- p_values plpdf_type.t_opt_array: value set of field
- p_value varchar2 default null: value of field
- p_default_value varchar2 default null: The default value to which the field reverts when a reset-form action is executed
- p_combo boolean default false: If set, the field is a combo box; if clear, the field is a list box
- p_edit boolean default false: If set, the combo box includes an editable text box as well as a drop list
- p_short boolean default false: If set, the field's option items should be sorted alphabetically
- p_read_only boolean default false: If set, the user may not change the value of the field
- p_required boolean default false: If set, the field must have a value at the time it is exported by a submit-form action
- p_noexport boolean default false: If set, the field must not be exported by a submitform action
- p_print boolean default false: If set, print the field when the page is printed
- p_x number: X coordinate for the field
- p_y number: Y coordinate for the field
- p_width number: The width of the field
- p_height number: The height of the field
- p_fill_color plpdf_type.t_color default plpdf_const.White: color for filling the field
- p_border_width number default 0: width of border of the field
- p_border_color plpdf_type.t_color default plpdf_const.Black: color of border
- p_font_size_auto boolean default false: If set, the text's size is automatic else use size of current font.
- p_hint varchar2 default null: The user name to be used when generating error or status messages for the field

Return: -

AcroForm_AddPushbutton

Type: procedure

Description: Add TextField.

Parameters:

- p_name varchar2: identifier of object
- p_label varchar2 default null: Caption of button
- p_x number: X coordinate for the field
- p_y number: Y coordinate for the field



- p_width number: The width of the field
- p_height number: The height of the field
- p_action varchar2 default null: supported actions:
 - o plpdf_const.button_action_submitform: A submit-form action transmits the names and values of selected interactive form fields to a specified uniform resource locator (URL), presumably the address of a World Wide Web server that will process them and send back a response.
 - o plpdf_const.button_action_resetform: A reset-form action resets selected interactive form fields to their default values.
 - o plpdf_const.button_action_javascript: A JavaScript action causes a script to be compiled and executed by the JavaScript interpreter.
- p_url varchar2 default null: when action is plpdf_const.button_action_submitform: A URL specification giving the uniform resource locator (URL) of the script at the Web server that will process the submission.
- p_submitformat varchar2 default null: when action is plpdf_const.button_action_submitform: format of submitted data
 - o plpdf_const.submit_format_html: HTML Form format
 - o plpdf_const.submit_format_fdf: Forms Data Format (FDF)
- p_request varchar2 default null: when action is plpdf_const.button_action_submitform: form of request
 - o plpdf_const.submit_request_post: using an HTTP POST request
 - o plpdf_const.submit_request_get: using an HTTP GET request
- p_IncludeNoValueFields boolean default false: If clear, fields without a value are not submitted.
- p_SubmitCoordinates boolean default false: when action is plpdf_const.button_action_submitform: If set, the coordinates of the mouse click that caused the submit-form action are transmitted as part of the form data.
- p_javascript varchar2 default null: when action is plpdf_const.button_action_javascript: A string containing the JavaScript script to be executed.
- p_print boolean default false: If set, print the field when the page is printed
- p_fill_color plpdf_type.t_color default plpdf_const.White: color for filling the field
- p_border_width number default 0: width of border of the field
- p_border_color plpdf_type.t_color default plpdf_const.Black: color of border
- p_font_size_auto boolean default false: If set, the text's size is automatic else use size of current font.
- p_hint varchar2 default null: The user name to be used when generating error or status messages for the field

Return: -

AcroForm_AddRadiobuttonField

Type: procedure

Description: Add RadiobuttonField.



Parameters:

- p_name varchar2: identifier of object
- p_values plpdf_type.t_radiobutton_array: value set of field
- p_value varchar2 default null: value of field
- p_default_value varchar2 default null: The default value to which the field reverts when a reset-form action is executed
- p_read_only boolean default false: If set, the user may not change the value of the field
- p_required boolean default false: If set, the field must have a value at the time it is exported by a submit-form action
- p_NoToggleToOff boolean default false: If set, exactly one radio button must be selected at all times
- p_noexport boolean default false: If set, the field must not be exported by a submitform action
- p_print boolean default false: If set, print the field when the page is printed
- p_height number: The height of the field
- p_gap number default 0: gap between graphical symbol and text
- p_fill_color plpdf_type.t_color default plpdf_const.White: color for filling the field
- p_hint varchar2 default null: The user name to be used when generating error or status messages for the field

Return: -

AcroForm_AddCheckBoxField

Type: procedure

Description: Add CheckBoxField.

Parameters:

- p_name varchar2: identifier of object
- p_label varchar2 default null: Caption of button
- p_checked boolean default false: If set, the checkbox is checked
- p_default_checked boolean default false: The default value to which the field reverts when a reset-form action is executed
- p_read_only boolean default false: If set, the user may not change the value of the field
- p_required boolean default false: If set, the field must have a value at the time it is exported by a submit-form action
- p_noexport boolean default false: If set, the field must not be exported by a submitform action
- p_print boolean default false: If set, print the field when the page is printed
- p_x number: X coordinate for the field
- p_y number: Y coordinate for the field
- p_height number: The height of the field
- p_gap number default 0: gap between graphical symbol and text
- p_fill_color plpdf_type.t_color default plpdf_const.White: color for filling the field
- p_hint varchar2 default null: The user name to be used when generating error or status messages for the field



Return: -



Version History

18-MAY-2005, v1.1.0

- PutImage
 - o p_type parameter removed
 - o PutImage supports the following file formats:
 - JPEG/JFIF
 - BMP
 - GIF
 - TIFF
 - PNG

22-MAY-2005, v1.1.1

- PutImage
 - o Fixed a bug: image size calculation

29-MAY-2005, v1.1.2

- PrintMultiLineCell
 - o Fixed a bug: borders
- PutImage
 - o Fixed a bug: error messages

09-JUN-2005, v1.1.3

- PrintMultiLineCell
 - o New parameters:
 - p_link
 - p_clipping
- GetImageProps: new function
- PrintImageCell: new procedure
- GetRowHeight: new function
- Row_Print2
 - o Fixed a bug: handling of p_maxline

30-JUN-2005, v1.1.4

- SetColor4Text
 - o Fixed a bug: handling of blue color
- GetPageWidth: new function
- GetPageHeigh: new function
- GetPageAvailableWidth: new function
- GetPageAvailableHeigh: new function



15-JUL-2005, v1.1.5

- Page size increased to 2Gb

31-JUL-2005, v1.1.6

- SetCellMargin: new procedure
- GetCellMargin: new function
- plpdf_type.t_color: new type
- GetColor4Drawing: new function
- GetColor4Filling: new function
- Plpdf_Const: new package (contains colors)
- SetColor4Drawing: new function with t_color parameter
- SetColor4Filling: new function with t_color parameter
- SetColor4Text: new function with t_color parameter
- GetLineWidth: new function
- SetColor4Drawing
 - o Fixed a bug: handling of blue color

31-AUG-2005, v1.1.7

- SetDashPattern: new procedure
- plpdf_type.t_point: new type
- plpdf_type.t_points: new type
- plpdf_type.t_pageformat: new type
- DrawPolygon: new procedure
- Pattern handling
 - o CreateTillingPattern: new procedure
 - o AddLine2Pattern: new procedure
 - o AddRect2Pattern: new procedure
 - o AddEllipse2Pattern: new procedure
 - o AddCircle2Pattern: new procedure
 - o AddPolygon2Pattern: new procedure
 - o SetTillingPattern: new procedure
 - o GetTillingPatternName: new function
 - o GetTillingPatternColor: new function
- Plpdf_Const: contains page formats
- Init1: new procedure

05-OCT-2005, v1.2.0

- nopAlias: new parameters
- AttachFile: new procedure
- SetPageNoStart: new procedure
- SetPageNoEnd: new procedure
- Image handling with and without Oracle Intermedia



08-NOV-2005, v1.2.1

- Certification uses only DBID for validating licence

30-NOV-2005, v1.2.2

- Row_Print: new parameter: p_fill
- Row_Print2: new parameter: p_fill
- AddTextAnnot: new procedure
- AddFileAnnot: new procedure
- AddHighlightAnnot: new procedure
- AddUnderlineAnnot: new procedure
- AddStrikeOutAnnot: new procedure
- GetPrintFontName: new function
- GetPrintFontStyle: new function
- GetPrintFontSize: new function

21-DEC-2005, v1.2.3

- Oracle XE support

31-MAR-2006, v1.2.4

- PrintCell: set p_w parameter's default value to 0
- PrintMultiLineCell: set p_w parameter's default value to 0
- LineBreak: change p_h parameter's type to NUMBER
- SetCurrentX: set p_x parameter's default value to 0
- Create integrated parameter checker for:
 - Init
 - Init1
 - SetHeaderProcName
 - SetFooterProcName
 - StartClipping
 - SetAllMargin
 - SetLeftMargin
 - SetTopMargin
 - SetRightMargin
 - SetAutoNewPage
 - SetDocDisplayMode
 - SetCompress
 - SetEncoding
 - NewPage
 - SetColor4Drawing
 - SetColor4Filling
 - SetColor4Text
 - SetLineWidth
 - DrawLine
 - DrawRect
 - AddTTF
 - SetPrintFont
 - SetPrintFontSize
 - SetLinkDest



- PutLink
- PrintText
- PrintCell
- PrintMultiLineCell
- PrintFlowingText
- LineBreak
- SetCurrentX
- SetCurrentY
- SetCurrentXY
- DrawEllipse
- PutImage
- CheckPageBreak
- SetRotate
- CrBookmark
- DrawSector
- SetProtection
- PrintImageCell
- SetCellMargin
- SetDashPattern
- DrawPolygon
- CrTillingPattern
- AddLine2Pattern
- AddRect2Pattern
- AddEllipse2Pattern
- AddPolygon2Pattern
- SetTillingPattern
- AttachFile
- AddTextAnnot
- AddFileAnnot
- AddMarkupAnnot
- Default Encoding in plpdf_cert package

01-JUN-2006, v1.3.0

- utf16 TrueType Font support
- Row_Print: new parameter: p_min_height
- Row_Print2: new parameter: p_min_height

15-SEP-2006, v1.4.0

- PrintCell: p_txt parameter length changed to 4000
- PrintMultiLineCell: p_txt parameter length changed to 4000
- PrintFlowingText: p_txt parameter length changed to 4000
- Row_Print2: new parameter: p_min_height
- GetScaleFactor: new function
- SetPrintFont: handling p_size is null
- Row_Print: fix a bug
- Row_Print2: fix a bug
- Table of Contents Commands
- Template related Commands



04-JAN-2007, v1.4.1

- Documentation changed

24-FEB-2007, v1.5.0

- AddCJKFont: new procedure
- Row_Print3: new procedure
- SetDocKeywords: p_keywords parameter length changed to 4000

21-MAY-2007, v1.5.1

- Streams: fix a bug
- Parser: handling number of pages

06-AUG-2007, v1.6.0

- PDF form (Acroform) support
 - o AcroForm_AddTextField: new procedure
 - o AcroForm_AddChoiceField: new procedure
 - o AcroForm_AddPushbutton: new procedure
 - o AcroForm_AddRadiobuttonField: new procedure
 - o AcroForm_AddCheckBoxField: new procedure
- SetNOLastpageProcName: new procedure
- Template: protection support
- OpenOffice Acroform filler (see extras\oo_form folder)

30-NOV-2007, v1.7.0

- Row_Print: fill fixed
- Template: encrypt fixed
- PrintFlowingText: p_txt parameter length changed to 32000
- PrintMultiLineCell: p_indent number default 0
- PrintFlowingTextLimit: new procedure
- TrueTypeUnicode automatic usage
- GetPageRightSpace: new function
- GetFontInfo: new function
- Row_Print4: new procedures
- SetCurrentY: new parameter
- CheckPageBreak: new parameter

23-JUL-2008, v2.0.0

- SetDocDisplayMode: doc extended
- native PNG support (PrintImageCell, PutImage p_type)
- use without InterMedia
- PrintFlowingTextLimit: bad charter handling fixed
- PrintMultiLineCell: bad charter handling fixed



- compress: LZW without Java
- SetCompress: new parameter: p_method
- plpdf_const package: new entries
- PutImage: new parameter: p_type
- PrintImageCell: new parameter: p_type

24-AUG-2008, v2.0.1

- PrintMultiLineCell: p_ln parameter added

24-SEP-2008, v2.0.2

- PrintFlowingText: p_clipping parameter added
- PrintFlowingTextLimit: p_clipping parameter added

06-OCT-2008, v2.0.3

- SaveTemplate: description update fixed

24-NOV-2008, v2.0.4

- Row_Print: p_clipping parameter added
- Row_Print2: p_clipping parameter added
- Row_Print3: p_clipping parameter added
- Row_Print4: p_clipping parameter added